

INNOVATIVE TECHNOLOGY LTD



# SSP DLL FUNCTIONS

A Windows® dynamic linked library file to allow easy development of SSP protocol on PC based systems.

Version 1.0

**Table of Contents**

Revision History .....	3
Introduction.....	4
Note.....	4
Main Functions .....	5
OpenPort .....	5
CloseComm.....	6
Command.....	7
Download Functions .....	8
DownloadFile.....	8
GetDownloadData .....	9
Utilities.....	10
SetRetryParameters.....	10
SetDTR .....	11
FlipSeq .....	12
GetLastRxPacket.....	13
GetLastTxPacket.....	14
Visual Basic declaration module for DLL Functions .....	15

**Revision History**

Issue Number	Date	Author	Comment
1.0	9/12/2003	T.Beswick	Initial document

**Introduction.**

To facilitate the implementation of SSP protocol on PC based systems, Innovative Technology Ltd have developed a DLL with a set of functions to allow easy access to the SSP commands and file downloading facility. Using this DLL, the programmer does not have to worry about packet formatting and CRC Generation; they are handled within the DLL.

The following shows descriptions, Visual Basic® declarations and some simple examples on how to use the functions. For a more detailed example of the implementation please see the Visual Basic® sample programs available from Innovative Technology.

**Note.**

This document is provided as a guide to the programmer. It is the users responsibility to test his/her implementation of the DLL to ensure the required operation. Innovative Technology Ltd does not accept liability for errors or omissions contained within this document and changes made from issue to issue.

## Main Functions

### OpenPort

**Function title:** OpenPort

**Parameters:** Port number (integer)

**Return value:** 1 if Port open successfully, 0 if error opening Port.

**Function Description:** To open a serial port ready for communication.

**Visual Basic® declaration:**

```
Public Declare Function OpenPort Lib "InnTechSSP.dll" (ByVal iPort As Integer) As Integer
```

**Example usage for Visual Basic®:**

```
Dim iPort As Integer
If OpenPort(iPort) <> 1 Then
    MsgBox "Error opening communication port", vbCritical, app.ProgramName
    Exit Function
End If
```

## CloseComm

**Function title:** CloseComm

**Parameters:** None

**Return value:** None

**Function Description:** Closes the open serial communications port.

**Visual Basic® declaration:**

Public Declare Function CloseComm Lib "InnTechSSP.dll" () As Integer

**Example usage for Visual Basic®:**

CloseComm

## Command

**Function title:** Command

**Parameters:** Command structure, UDT

**Return value:** UDT containing return data. The datalen parameter is the number of bytes in the data array. The data array, array1 contains the return data.

**Function Description:** Sends an SSP command to an open serial port. The UDT data structure is loaded with the data length (how many bytes in the command array). The command array contains the command and any data. rxStatus is set to the SSP address of the slave device (defaults to 0)

**Visual Basic® declaration:**

```
Public Declare Function Command Lib "InnTechSSP.dll" (Src As UDT) As UDT
```

**Example usage for Visual Basic®:**

```
Public Const POLL_CMD = &H7
```

```
Public Const OK = &HF0
```

```
' the user defined structure
```

```
Public Type UDT
```

```
    rxStatus As Integer
```

```
    datalen As Byte
```

```
    array1(254) As Byte
```

```
End Type
```

```
Dim Cpy As UDT, Src as UDT
```

```
' send Poll command
```

```
Src.datalen = 1
```

```
Src.array1(0) = POLL_CMD
```

```
Cpy = Command(Src)
```

```
If Cpy.array1(0) <> OK Then
```

```
    MsgBox "Validator comms error", vbCritical, App.ProductName
```

```
    CloseComm
```

```
    Exit Function
```

```
End If
```

```
' Cpy.Array1 now contains the event list for the slave
```

## Download Functions

### DownloadFile

**Function title:** DownloadFile

**Parameters:** filename (string), Port number (integer)

**Return value:** number of blocks or error code

**Function Description:** Will download an ITL ssp download file to a slave device. The entire header checking and handling is done within the DLL. This function will open the passed filename, check the header is valid, test for a connection to a validator and then start the download process thread, which will then run in the background. After the thread has been started, the function will return the number of blocks to download or (if this number is  $\geq$  OPEN\_FILE\_ERROR) an error code.

If an error code is returned, the background thread is terminated. When the total number of blocks has been downloaded (or an error has occurred), then the thread terminates. The user can test the download process at intervals using the GetDownloadData function. The normal procedure would be to call the DownloadFile function with a valid filename and comport number and then, if a valid number of blocks has been returned, start a timer to check to download progress using the GetDownloadData function.

**Visual Basic® declaration:**

```
Public Declare Function DownloadFile Lib "InnTechSSP.dll" (ByVal szName As String, ByVal iport As Integer) As Integer
```

**Example usage for Visual Basic®:**

( See the example Visual Basic® program SSPFileDownload for complete listing)



## **GetDownloadData**

**Function title:** GetDownloadData

**Parameters:** None

**Return value:** number of current download block or error code

**Function Description:** Function to return the current status of the download process thread. Will return the number of the current download block or if this number is  $\geq$  OPEN\_FILE\_ERROR, then this is an error code. A successful download will return DOWNLOAD\_COMPLETE.

**Visual Basic® declaration:**

Public Declare Function GetDownloadData Lib "InnTechSSP.dll" () As Integer

**Example usage for Visual Basic®:**

( See the example Visual Basic® program SSPFileDownload for complete listing)

## Utilities.

### SetRetryParameters

**Function title:** SetRetryParameters

**Parameters:** Data structure

**Return value:** always 0.

**Function Description:** To set up SSP retry parameters. At start up , DLL will have retry parameters set to 10 tries at 1 second intervals. Using this command, the user can adjust these. The retry time can be set to multiples of 1 second (minimum time 1 second). This can be useful for providing a faster time-out when checking for an initial validator connection. It is recommended that the user reset the parameters to default values of 10 retries at 1 second intervals when polling the slave device, especially when polling the NV4 validator as this device has to turn off serial interrupts during time-critical operations so will not respond to commands some times.

**Visual Basic® declaration:**

```
Public Declare Function SetRetryParameters Lib "InnTechSSP.dll" (rRtry As RTRY) As Integer
```

#### Example usage for Visual Basic®:

```
Public Type RTRY
    rDelay As Byte
    rRetries As Byte
End Type
```

```
Dim i as integer
Dim rRtry as RTRY
```

```
    rRtry.rDelay = 1
    rRtry.rRetries = 3
    i = SetRetryParameters(rRtry)
```

## SetDTR

**Function title:** SetDTR

**Parameters:** DTR value, integer

**Return value:** Integer, 1 if DTR set, 0 if error.

**Function Description:** To set or reset the DTR pin on the serial port connector. This may be useful for some hardware interfacing projects when communicating with a slave device using SSP. Open the serial port and set the DTR value to 1 to set DTR pin high, clear the DTR value parameter to set pin low.

**Visual Basic® declaration:**

```
Public Declare Function SetDTR Lib "InnTechSSP.dll" (ByVal iDTR As Integer) As Integer
```

**Example usage for Visual Basic®:**

```
Dim iPort As Integer, i as integer
```

```
    If OpenPort(iPort) <> 1 Then
```

```
        MsgBox "Error opening communication port", vbCritical, app.ProgramName
```

```
        Exit Function
```

```
    End if
```

```
    i = SetDTR(0) ' clears the DTR Pin
```

```
    i = SetDTR(1) ' sets the DTR pin
```

## FlipSeq

**Function title:** FlipSeq

**Parameters:** None

**Return value:** Integer, always 1.

**Function Description:** Flips over the next sequence bit. So if the DLL were going to send a 1 with the next command, it would now send a zero. This command was only useful during diagnostic programming of the DLL, but has been included here as a utility.

**Visual Basic® declaration:**

Public Declare Function FlipSeq Lib "InnTechSSP.dll" () As Integer

**Example usage for Visual Basic®:**

Dim i as integer

i= FlipSeq

## GetLastRxPacket

**Function title:** GetLastRxPacket

**Parameters:** None

**Return value:** UDT structure

**Function Description:** When called, returns a UDT structure containing a datalength byte and an array of bytes which are the full SSP formatted packet of the last received ssp command (from slave). Useful for creating log files of packet data.

**Visual Basic® declaration:**

```
Public Declare Function GetLastRxPacket Lib "InnTechSSP.dll" () As UDT
```

**Example usage for Visual Basic®:**

' the user defined structure

```
Public Type UDT
```

```
    rxStatus As Integer
```

```
    datalen As Byte
```

```
    array1(254) As Byte
```

```
End Type
```

```
Dim cpy as UDT
```

```
    cpy = GetLastRxPacket
```

```
    'cpy.array contains the full SSP packet
```

## GetLastTxPacket

**Function title:** GetLastTxPacket

**Parameters:** None

**Return value:** UDT structure

**Function Description:** When called, returns a UDT structure containing a datalength byte and an array of bytes, which are the full SSP formatted packet of the last transmitted ssp command (to slave). Useful for creating log files of packet data.

**Visual Basic® declaration:**

```
Public Declare Function GetLastTxPacket Lib "InnTechSSP.dll" () As UDT
```

**Example usage for Visual Basic®:**

' the user defined structure

```
Public Type UDT
```

```
    rxStatus As Integer
```

```
    datalen As Byte
```

```
    array1(254) As Byte
```

```
End Type
```

```
Dim cpy as UDT
```

```
    cpy = GetLastTxPacket
```

```
    'cpy.array contains the full SSP packet infomation
```

## Visual Basic® declaration module for DLL Functions

```

Public Const DOWNLOAD_COMPLETE = &H100000
' error code definitions
Public Const OPEN_FILE_ERROR = &H100001
Public Const READ_FILE_ERROR = &H100002
Public Const NOT_ITL_FILE = &H100003
Public Const PORT_OPEN_FAIL = &H100004
Public Const SYNC_CONNECTION_FAIL = &H100005
Public Const SECURITY_PROTECTED_FILE = &H100006

Public Const DATA_TRANSFER_FAIL = &H100010
Public Const PROG_COMMAND_FAIL = &H100011
Public Const HEADER_FAIL = &H100012
Public Const PROG_STATUS_FAIL = &H100013
Public Const PROG_RESET_FAIL = &H100014
Public Const DOWNLOAD_NOT_ALLOWED = &H100015

'dll function to open a comms port (iPort)
Public Declare Function OpenPort Lib "InnTechSSP.dll" (ByVal iPort As Integer) As Integer
'dll function to close a comms port
Public Declare Function CloseComm Lib "InnTechSSP.dll" () As Integer
'dll function to set port baud rate
'dll function to send an SSP command and receive a reply
'the command is sent and returned in the form of a structure (UDT)
'rxStatus is not used when sending, datalen is the number of command bytes
'array1 contains the array bytes
Public Declare Function Command Lib "InnTechSSP.dll" (Src As UDT) As UDT

Public Declare Function SetRetryParameters Lib "InnTechSSP.dll" (rRtry As RTRY) As Integer
'sets/resets the DTR pin (0 and 1)
Public Declare Function SetDTR Lib "InnTechSSP.dll" (ByVal iDTR As Integer) As Integer
'set the sequence byte (0 or &h80)
Public Declare Function FlipSeq Lib "InnTechSSP.dll" () As Integer
Public Declare Function GetLastRxPacket Lib "InnTechSSP.dll" () As UDT
Public Declare Function GetLastTxPacket Lib "InnTechSSP.dll" () As UDT

Public Declare Function DownloadFile Lib "InnTechSSP.dll" (ByVal szName As String, ByVal iPort As Integer) As long
Public Declare Function GetDownloadData Lib "InnTechSSP.dll" () As long

'the user defined structure
Public Type UDT
    rxStatus As Integer
    datalen As Byte
    array1(254) As Byte
End Type

Public Type RTRY
    rDelay As Byte
    rRetries As Byte
End Type

```