

OCX driver (USB)

To check the printer status via OCX driver,


First, you should install the ocx driver.

Second, you should change the model number in the program provided.

Well, let's take a look at the way how to install the ocx driver first.


1. How to install the ocx driver.

1.1. Please double click the sample program as below.




1.2. Please double click the file (project1.vbp) as below.


Notice : You should have the visual basic program.



1.3. Then you can see the screen as below.




1.4. Please click the right button of mouse, and you can see the box is highlighted Red.



1.5. Then you can see the box is highlighted in Red as below.


Please make sure that HwaUSB ActiveX Control module is ticked.

Please click the search as the image below.




1.6. Please search the ocx driver you want to install. Please refer to the image as below.

Then you have completed the installation of ocx driver.



2. How to change the model.


2.1. If you double click Form1(Form1.frm), you can see the image below.




2.2. If you double click the code as image, you can see the code (source) as below.

Also you can see the number HMK-825 which is highlighted Red.

Well, as of now, we should change all of the number HMK-825 into the number you want.



2.3. Please follow the steps, such as First, Second.




2.3. Please follow the steps, such as Third, Fourth.

Third, please fill out the models at the blanks.


Fourth, please click the button to change all of the number.

```
Private Sub Command1_Click()  
Dim a  
Dim X As Printer  
Dim pic As Picture  
PrintMode = 1  
search for windows target printer priter  
SUCCESS = False  
For Each X In Printers  
If X.DeviceName = "HWAUSUNG HMK-825" Then  
Set Printer = X  
SUCCESS = True  
Exit For  
End If  
Next  
If Not SUCCESS Then  
MsgBox "There is no Target Printer(HWAUSUNG  
End If  
  
For i = 1 To Text2.Text  
wait:  
DoEvents  
Printer Status Check before Print  
a = HwaUSB1.RealRead  
Call Status_Display(a)  
Printer End check!  
If (a And 16) Then  
GoTo wait ' print not end  
Else  
' print end then next print  
End If  
Printer error check!  
If (a And &HE7) Then ' Near End and printing flag Mask,3rd bit(Can Print)  
GoTo wait  
Else  
End If  
End If
```

2.4. You can see the screen is highlighted in Red. You have completed the change.





2.5. Please make sure the number is changed.



2.6. Please click the icon to check the printer status. Then, you can see the printer status as imaged, and following images.

Notice : Please make sure the printer has to power on / the cable should be connected with the host, before you click the icon to check.



For your reference

Functions

1) long HwaUSB1.Open(LPCTSTR SelPrinter);

Please open USB port as Printer Model("HMK-060").

- Parameters:
SelPrinter : Printer Model Name
- Return :
Open normal : 0
Open error : -3(minus)

2)void HwaUSB1.Close(void);

Please close USB port by the way of which you open Printer Model.

- Parameters:
None
- Return :
None

3)long HwaUSB1.PrintStr(LPCTSTR data);

It prints the string.

- Parameters:
data : String datas
- Return :
Print normal : 1
Print error : 0

※ In order to prevent the data loss by the printing timeout,

Please check the printer status by the RealRed function, and print out.

4)long HwaUSB1.PrintCmd(unsigned char data);

It prints the data 1 byte. It is to use for the printer control command.

■ Parameters:

data : 1 byte data (0~255)

■ Return :

Print normal : 1

Print error : 0

5)long HwaUSB1.RealRead(void);

It reads the data of printer status as 1 byte of USB port.

■ Parameters:

None

■ Return :


Read normal : Printer status

Read error : -1(minus)

※ Please do not use the functions which are not commented.

NOTICE 1

If you use the ocx and windows drivers together, the data will not be printed in regular sequence.
So please release the spool, when you want to use the OCX driver, and window driver together.
If you release the spool, the data receipt is only made by OCX.



Notice : Please refer to the following data flow chart of window application

